

Save File List

The “Save File List” menu option (on the File menu) allows you to save a list of the files you’ve marked with the Back Up Files option. If you often back up the same set of files, select this option from the pull-down menu and give the set a name. Then you can use that set when you back up by file the next time.

Preferences

The Special menu’s “Preference” option displays the Archiver Preferences dialog (Figure 10M).




Figure 10M—Archiver Preferences Dialog

- *Verify disks after writing*—makes sure that the archived data was written correctly after filling a backup disk. We recommend leaving this option checked.
- *Erase destination media without asking*—allows the Archiver to erase the disks you’re using for your backup without asking first, even if there’s already something on them.
- *Interrupt backup for file read error*—If you have errors on your hard drive but want to continue backing up your hard drive in the event of an error (to back up all the good files), uncheck this option.
- *Compress volume backup*—Uses data compression to make backing up a volume smaller.
- *Volume back up only blocks in use*—For most disks, you can leave this option checked. If the volume’s bitmap is damaged or invalid, you can uncheck this option to back up all the blocks on the disk, even if they’re not marked as being used by files.